



- Download Center

Intel® Server Board  
S5000PAL

[Additional Downloads](#)

[Support Information](#)

[RSS Feed](#)

Select a language for  
**Download Center**

English

# Downloads

## Download Assistance

- To begin the download process, click Download.
- For additional details about this download, click Read Me or Release Notes (not available for all downloads).

### RAID WEB Console Utility for Windows\*

#### Supported RAID Controllers

This download supports Intel® RAID controllers using SAS software stack (SRCASAS18E, SRCASAS144E and SROMBSAS18E) and Intel Embedded Server RAID Technology II RAID products (on server boards enabled for S5000 (ESB2) SATA RAID and LSI1064e/1068 SAS RAID), please verify that this utility has been tested with the RAID card you have chosen to use by checking the drivers web page for your controller at <http://support.intel.com>.

#### Package Information

version = 1.19-00

OS supported = Windows\* 2000, Windows\* 2003, Windows\* XP

This package can be installed on all x86 and x64 systems.

#### Contents on the package

This package includes the Java Runtime Environment files as well as the Web Console2 installation files.

#### Installation Instructions

See Detailed installation instructions below:

1. Extract the contents of the ZIP file and run Setup.exe from the Disk1 folder.

If JRE is not already installed, the setup program will install the appropriate version and reboot.

2. Choose from four options:

- Complete: Installs all features.

- Client: Allows the local system to administer and configure all the RAID servers in the network, but not the local system.

- Server: Allows the local server to be managed remotely.

- StandAlone: Allows the local server to be managed only by itself. This installation can neither manage other servers nor allow other clients to manage this server.

If you do not see the choices in #2, the program has determined you have a client only system with no Intel(R) RAID installed or 1.19 was installed over a previous version and kept the same mode.

If a security warning about "popup" appears, click "allow" if you wish to receive alerts.

Windows 2000 note: Authentication requires the admin privilege setting. To enable, go to Program --> Administrative Tool --> Local Security Settings. Assign the policy "Act as part of operating System" to user (Administrator / Everyone).

To start the utility, go to Start>Programs>RAID Web Console 2 and choose StartupUI. You will be notified if no supported RAID controllers are found.

Silent install is available using the command:

```
Setup.exe /s /v"/qn SETUPTYPE=
```

where setuptype may be Client or Server.

Please refer to the Readme file for additional information.

[Read Me](#) (txt)

---

**English:** ir3\_Windows\_RWC2\_v1.19-00.zip

**Download**

Ver:1.19-00

Date:3/13/2007

Size:18124 (KB)

Time @56Kbps:41.95 min

**OS:**Windows Server\* 2003, Windows Server\* 2003 Enterprise x64 Edition, Windows\* 2000 Advanced Server, Windows\* Storage Server, Windows\* XP Professional x64 Edition

---

This download is also valid for the products listed below. Use the links below for additional product downloads:

[Intel® RAID Controller SRCAS144E](#)

[Intel® RAID Controller SRCAS18E](#)

[Intel® Server Board S5000PAL](#)

[Intel® Server Board S5000PSL](#)

[Intel® Server Board S5000VCL](#)

[Intel® Server Board S5000VSA](#)

[Intel® Server System SC5400RA](#)

[Intel® Storage Server SSR212MC2](#)

[Intel® Storage Server SSR212MC2R](#)

[Intel® Workstation Board S5000XVN](#)